

Aduro Hybrid App & Firmware Update

We continuously improve the Aduro Hybrid app and stove firmware to enhance stability, safety, and ease of use. Most releases include a combination of performance improvements, bug fixes, language updates, and new features supporting additional stove models and markets. Below you can find the details of the latest update.

January 2026 Release

App: Android 3.09 / iOS 3.25

Firmware: 706.16

Major Improvements

- Improved ignition detection
 - This update improves how the stove detects ignition, making the start-up process more reliable. During start-up, the system now checks that the temperature increases by at least 12 °C. It then verifies ignition over the next 15 minutes, during which the temperature must rise by an additional 10 °C. The igniter operates for up to 15 minutes or until the temperature reaches 90 °C. If ignition fails, a new start attempt will only begin once the temperature has dropped below 85 °C. These improvements help prevent false start attempts and ensure more stable stove operation.
- Improved alarm structure and alarm messages
- Improved firmware update stability
- Improved crash handling on iOS 18 and Android
- Improved text display during manual firmware updates
- Improved handling of grey screen issues on some Android devices

New Features

- Added support for new stove models
- Time zone setting available in app
- Cloud messages are now supporting hyperlinks
- Added dynamic sliders in the adjustment menu
- Full-screen mode – swipe up to show the navigation bar

If your smartphone or tablet does not automatically install updates, you can update the app manually through your app store:

App Store (iOS):

<https://apps.apple.com/dk/app/aduro-hybrid/id1499349672>

Google Play (Android):

<https://play.google.com/store/apps/details?id=com.nbe.android.adurohybrid1>

It is important that both the app and the stove have the latest software version to ensure proper functionality.

If you have any questions or need assistance, please feel free to contact us at service@aduro.dk.